
Monitoring objects through the Google Earth program

Create the tracking link ot the livegpstracks.com

- → Create a tracking link. How links are created is described here
- → In the link creation window, activate "NetworkLink for Google Earth"
- → Optionally fill in the name of the link. The name will not be transferred to Google Earth, but only serves as a reminder in the settings.
- → If you want to limit the viewing period, fill in the date fields. The movement of the tracker on the created link will be displayed only during the specified period.
- → Click the "Add" button

Without group		Create a new group	
Model	IMEI	Private tracking links	
1. RealTimeTracker for Android Real Time Gps Tracker App	b4626a57c3ad7368	1: https://livegpstracks.com/dv_35916926901339828937053.html	
RTT Configurator		NetworkLink Google Earth:	
RTT Commands		Link description:	
Parameters settings		NetworkLink Google Earth	
Group: not set		Password (can be left empty):	
Time corr.: 3 🕡		Date and time of the displaying (permanent if empty):	
Speed corr.: 0 0		Clean Clean Clean Clean	
Icon:		☐ Disable the track review ☐ Enable chat ☐ Enable chat for guests	

The link should appear in the list.



By default, it is assumed that the link is used to track a single tracker, so the "Fly to View" option is enabled and the camera follows the object as it moves.


If several links are added to Google Earth, then this behavior becomes inconvenient - the camera starts constantly "jumping" from one object to another. Due to a bug in the "Google Earth" program itself, setting this parameter in the link settings does not work. Therefore, it can be set in the link

The parameter is called flytoview. To disable camera movement, it must be equal to zero -"flytoview=0". An example of adding a parameter:


http://livegpstracks.com/livekml 00000000000000000000.kml?flytoview=0

How to insert a link in Google Earth

- → Copy the address of the link created in the previous step to your clipboard
- → Open Google Earth
- → Menu "Add" → Item "Network Link"



- → In the dialog that appears, paste the link address from the clipboard into the "Link" field
- → Optionally, enter text in the "Name" field
- → Click "OK" button



The added link should be displayed in the left field of the program. Select element and the tracker will appear on the map. Now you can watch the movement of the tracker online in Google Earth.



The option is available on the tariffs: "Simple", "Professional"

https://help.livegpstracks.com/ - LiveGPStracks.com

Permanent link:

https://help.livegpstracks.com/doku.php?id=monitoring_through_the_google_earth

Last update: 2023/08/27 23:02

